## P2 Plug-In Ex Guide for Media Composer 2019 Rev 1.0


This is operation guide for P2 Plug-In Ex regarding modified GUI part of Media Composer 2019. Please refer operation manual AJ-PS001G-004G(VQT5G96-4)\_E for other part of it.

### 1. How to import P2 Clip

1.1. Navigate "File" > "Input" > "Source Browser" to open Source Browser dialog.

File Edit Bin Clip TimeJin	e Composer	Tools	Windows	5cript	Avid Link	Help
New						
Open Bin	Ctri+O					
New Bin Container						
Close Project	Ctrl+Shift+V					
Input		, 5	ource Brow	iser		
Output			mport Med	a		
Media			ape <u>C</u> aptur	e	Ctr	H7
		É	ink to Yolu	me for E	Бкропт	
		import EOL				
Settings	Orl+Shift+=		CURRENT ATTER			

1.2. Select the upper folder of CONTENTS folder by Source Browser, then press Link or Import so that Clips in CONTENTS folder are displayed to specified Target Bin.




# 2. How to Export P2 Clip

2.1. Navigate "File" > "New" > "Volume for Export"

Elle Edit Bin Clip Timeli	ine Composer	Too	ls <u>Windows</u>	Script Avid Li	nk Help
New			New Bin	Ctrl+N	
Qpen Bin	Ctrl+O		Volume for Export		
New Bin Container			New Script	í Í	
Close	Ctri+W				

2.2. Select "Panasonic P2" at Volume Type in the Export Volume dialog.



#### **2.3.** Set several settings at Export Volume dialog.

- ① Specify the name of Volume Bin (It cannot specify already used name)
- 2 Select video compression format
- **3** Select Audio Bit Depth
- (4) Select P2 Card or the Folder of other recording media
- $\bigcirc$  If select Folder, press Set button and enter the folder name
- Select "Spanned" if desired to divide 4GB each, if not, select "Non-Spanned" 6 Specify each meta data if needed.


"Load from XML" button allows to import XML under P2 Clip, or pre-stored XML metadata. "Save XML" button allows to store current medatada set in XML form.

Press OK after all settings are done.

			Eg	port Volume				
	Volume Type: Finador	nr.PZ (*						
1	Volume Bin Names - New Yolum e							
1 2	Video Format	AVCLongG25 1080	N/59.94 +					
	File Format	P2 Format *						
3	Audio Bit Depth	24 部に *						
0	Export Ta:							
						I		
4		P2 Card						
0								
5 -			Set.	Folder: C:/Avid MediaFiles				
۲				Non-Spann	ed -			
	Creator							
6	Shot Mark							
U	Text							
	Scenario							
	-⊮ Use			Program Name				
	Scene No.			Take No.				
	News							
	2 Use			Reporter				
	Purpose			Object		_		
	Load from XML							
	Save to XML							
	Construction of the local distance of the lo				0	K Cancel		
7	Concerned Address					and the second sec		


2.4. Setting is done if new tab is added in a Bin.

e Composer <u>T</u> ools <u>W</u> b 1080i59 8in2		zipt Avid Link F New Vo ▼ III ₩ 10		× •
Export Volume: Panasoni	c P2 Sint	Location: C:\Avid	d MediaFiles	
Color		Name	Media Sta	atus




### 2.5. Drag & drop Sequence file into Export Volume


Dropped Sequence is indicated Yellow at Media Status column




2.6. Export is started by pressing Commit button. No other operation is possible while export. Multiple sequences are exported one by one by adding each sequence in the list before pressing Commit button.



2.7. Progress bar is displayed when export is started. Please wait until closed.




2.8. Sequence is gone when export is finished, and exported clip is loaded and displayed, where the Media Status is turned to Green.



#### < NOTE >

- 1. Frame rate, etc. is same as project setting, so only available option is selectable.
- 2. Please wait until completed. It is not correctly exported if remove media while exporting.
- 3. Following raster sizes are supported.
- 4K-DCI:4096x2160, UHD:3840x2160, 2K:2048x1080, 1080:1920x1080, 720P:1280x720
- 4. If one of the clip is not same video format as project setting, please transcode clip before export by "Clip" > "Consolidate/Transcode" in order to match the video format.
- 5. Please make sure if "Location" is correct. It might be different between selected P2card and actual location due to mount order of inserted P2 card.



#### \* Revision History

Oct. 15, 2019	Rev1.0	original					