AK-UB300 Firmware update procedure

1. Preparation

CAUTION : Before Updating Software

Do not power down while upgrading.

If the program quits during loading, the data will be erased or part writing condition and the restart is not made.

This is explanation how to updating using the UB300 Setting Tool. Updating procedure in WEB Screen and the other functions of the UB300 Setting Tool, please refer to the Operating Instructions.

< Installation of UB300 Setting Tool >

Download the UB300 Setting Tool from following website. <u>http://pro-av.panasonic.net/en/</u> Service and Support

For Windows

Perform the installation logged in as a user with the administrator privilege. Double-click the downloaded file. The file is expanded and setup.exe is displayed. Double-click setup.exe. The introduction screen is displayed. From hereafter, install following the instruction of the installer.

For Macintosh

Perform the installation logged in as a user with the administrator privilege. Double-click the downloaded file. The file is expanded and UB300SettingTool.app is displayed. Move UB300SettingTool.app to the Application folder or appropriate location.

< Download the update file >

- Accept the software usage agreement and download the update file data "DV91000067*.zip" for the AK-UB300 firmware from the following support web site. <u>http://pro-av.panasonic.net/en/</u> Service and Support
- 2. Extract the "**DV91000067***.**zip**" file.

2. Connection

1. Connect the personal computer to operate the UB300 Setting Tool and AK-UB300 as follows.



2. Set the IP address of the personal computer with a separate address of AK-UB300 within the range of private address. Set the subnet mask to the same address as AK-UB300.

IP address and subnet mask of the camera (factory settings) IP address:192.168.0.40 Subnet mask: 255.255.255.0 Private address range: 192.168.0.0 to 192.168.0.255

(Example) Personal computer: 192.168.0.100 AK-UB300: 192.168.0.40

- 3. Startup the UB300 Setting Tool
 - For Windows Click [Start] \rightarrow [Program] \rightarrow [Panasonic] \rightarrow [UB300 Setting Tool].
 - For Macintosh

Double-click the [UB300 Setting Tool] icon in the Application folder or your customized folder from [Finder].

4. Connection Setting Click [Connection Setting] button

Status	unertico Settina	
No Status	initiation Security	
Connection Setting		
Firmware Update	Camera IP Address : 192.168.0.40 Port : 80	1
Main Menu		
SWITCH MODE	Authentication	i ,
PAINT	User Name : Password :	
SYSTEM MODE	Local Hest	
IN/OUT SELECT	Port: 31004	
FILE		
	model:	
	Connact	
OSD Menu Operation		
On / Off Exit		
1		
BAR CAM		
1000 C		

Set the IP Address and other required items.

[Camera] (Figure-1)

[IP Address]

Sets the IP address of AK-UB300 to be connected.

[Port]

Sets the port number of AK-UB300 to be connected.

This setting is not necessary when the HTTP port number at the AK-UB300 side is not changed from its default.

[Authentication] (Figure-2)

[User Name]

Specifies the account name used to connect to AK-UB300. Specify the account with the administrator privilege. [Password]

Specifies the password for the account to be used when connecting.

Default User Name: admin Password:12345

[Local Host] (Figure-3)

[Port]

Specifies the communication port number of the personal computer where the UB300 Setting Tool is to operate.

[Connect] button(Figure-4)

Connection to AK-UB300 will start when the [Connect] button is clicked after setting [IP Address]/[Port]/[User Name]/[Password].

[AK-UB300] is displayed in [Model] when the connection is successful.

3. Update procedure

- 1. Click [Firmware Update] button in UB300 Setting Tool.
- 2. [Camera Information] (Figure-1) Displays the current version of the firmware for the connected AK-UB300.

VERSION	version of all the firmware
CAM MAIN	software version of the camera
NETWORK	version of the network software
ROM TABLE	version of the camera table
CAM FPGA	FPGA version of the camera
AVIO FPGA	version of AVIO FPGA
Option	(enabled only when an option board is added)

- [Select the firmware folder] (Figure-2) Select the folder storing the firmware file to write to AK-UB300.
- 4. [Firmware file information] (Figure-3) The firmware files required to update are detected and are selected in check-box. You can also select any firmware to update.
- 5. [Execute] (Figure-4)

Click [Execute] button to execute updating.

	Firmware Update				
nnect	Camera Information				
Connection Setting	Camera	Model :		AK-UB300	
Firmware Undate	VERSION :			05.00-000-00.00	
	CPU Software	CAM MAIN :		01.00-000-00.00	
Menu		NETWORK :		01.00-000-00.00	
SWITCH MODE	EEPROM	ROM TABLE :		01.00-000-00.00	
PAINT	FPGA	CAM FPGA ;		01.00-000-00.00	
SYSTEM MODE		AVIO FPGA :		01.00-000-00.00	
	Ontion				
	Firmwore file informa	tion			
	T in inware the intorne				
	CPU Software	CAM MAIN :	 		
		NETWORK :	 		
Menu Operation	EEPROM	ROM TABLE :	 		1
/ Off Exit	FPGA	CAM FPGA :	 		
1		AVIO FPGA :	 		
	Option		 		
•					
- <u>OK</u> →				Execute	

Do not power down while updating.

The progress bar will be appeared while updating. (The figure below as example) Software update may take approx.40 min. Blinks in green during the firmware update. Do not perform any operation during the update until the update is completed.

1/2	Currently updating
Total	20%
	Elapsed time 02:39

6. The message will be appeared when update is completed.

ted successfully.
ОК

7. Click to "OK" button and the connection setting display will be appeared. Click [Connection] button, then select [Firmware Update] to confirm the firmware version.